

Zenkuman[®]
IEEE1394
Digital Camera Library
(ZCL-1)

Application Programming
Interface Specification

Technoscope Co., Ltd.

History

2005/09/12	First edition
2005/10/03	Description on ZCLOpen is changed. Way to use the standard value of ZCLCreateConvHandle is added. Incorrect description on ZCLSoftTrigger is corrected. Incorrect description on ZCLSetCallBack is corrected. A function is added. ZCLCameraInfo
2005/10/14	Description on ZCLImageCompleteWait is changed.
2005/11/02	Example in which ZCLSetCallBack is used is added. Incorrect description on ZCLGetLastError is corrected. Incorrect description on ZCLCameraInfo is corrected. Description on ZCLCameraInit is added. Description on ZCLSaveMem is corrected. Description on ZCLLoadMem is corrected. Description on ZCLIsoStart is corrected.
2006/01/20	ZCLColorConvSetBMPINFO function is added. ZCLSetPktSize function is added. ZCLCheckHitachi function is added. ZCLHMaskingOff function is added. ZCLHMaskingOn function is added. ZCLGetHMasking function is added.
2006/03/14	ZCLGetExtModeInfo function is added. ZCLImageCompleteWaitTimeOut function is added. The explanation of the structure definition is added. The explanation of the constant definition is added.

Contents

1. Outline.....	1
2. Development Operation and Operating Environment.....	2
3. Description of Functions.....	3
4. Important Notes.....	87

No part of this manual shall be reproduced or stored in an electronic retrieval system or other system without written permission from the publisher.

1. Outline

This specification describes the software of IEEE1394 Digital Camera Library “ZCL-1”. This is a functional specification for operating an IEEE1394 Digital Camera in the Windows operating environment of a DOS/V personal computer using “ZCL-1”.

2. Development Operation and Operating Environment

Application creation and operating environment in this specification

- | | | |
|---------------------------------------|---|---|
| 1) Computer | : | IBM (DOS/V) personal computer |
| Expansion bus | : | Conforms to PCI revision 2.2.
One or more empty expansion bus |
| OS | : | Windows XP
Windows 2000 |
| CPU | : | Intel Pentium 233 MHz or higher |
| Memory | : | Mounting capacity of more than 64M byte |
| Hard disk | : | Mounting capacity of more than 1G byte |
| | | |
| 2) IEEE1394 extended board | : | Zenkuman PFW-85 (made by Technoscope)
Zenkuman PFW-86 (made by Technoscope) |
| | | |
| 3) Dedicated software | : | ZCLDrv.sys IEEE1394 interface card device driver
ZCL.dll ZCL.API |
| | | |
| 4) Development environmental software | : | Conforms to Microsoft Visual C++. |

Caution)

The person in charge of development requires C language-based software development experience in the Windows operating environment when using this software. Understanding the IEEE1394 Digital Camera Specification enables software to be developed smoothly.

3. Description of Functions

3.1 ZCL-1 Function List

1. Outline.....	1
2. Development Operation and Operating Environment.....	2
3. Description of Functions.....	3
3.1.1. Setting of system callback function	5
3.1.2. Acquisition of error code	7
3.1.3. Acquisition of connection camera list.....	8
3.1.4. Start of camera use.....	9
3.1.5. Stop of camera use.....	10
3.1.6. Entire stop of camera use.....	11
3.1.7. Acquisition of camera information	12
3.1.8. Confirmation of camera connection.....	13
3.1.9. Initialization of camera	14
3.1.10. Confirmation of camera mode	15
3.1.11. Setting of camera mode	17
3.1.12. Acquisition of camera mode	19
3.1.13. Acquisition of enhancing mode information	20
3.1.14. Saving of memory channel	21
3.1.15. Read of memory channel	22
3.1.16. Confirmation of camera mounting function.....	23
3.1.17. Acquisition of camera parameter value	24
3.1.18. Setting of camera parameter value.....	26
3.1.19. Securing of communication resources	29
3.1.20. Release of communication resources	30
3.1.21. Start of communication.....	31
3.1.22. Stop of communication	33
3.1.23. Acquisition of image information	34
3.1.24. Setting of image information	35
3.1.25. Setting of packet size	37
3.1.26. Acquisition request of image data.....	39
3.1.27. Acquisition completion wait of image data	41
3.1.28. Acquisition completion wait of image data (with time-out)	43
3.1.29. Acquisition cancellation of image data.....	45
3.1.30. Execution of soft trigger	46

3.1.31. Read of camera control register	47
3.1.32. Read of register.....	48
3.1.33. Write of camera control register	49
3.1.34. Write of register	50
3.1.35. Acquisition of library revision	51
3.1.36. Reinitialization of isochronous resources	52
3.1.37. Creation of color conversion table.....	53
3.1.38. Opening of color conversion table.....	55
3.1.39. Entire opening of color conversion table	56
3.1.40. Execution of color conversion	57
3.1.41. Setting of BITMAPINFO information.....	59
3.1.42. Confirmation of Hitachi Kokusai camera model	60
3.1.43. Setting of masking	61
3.1.44. Release of masking setting.....	62
3.1.45. Acquisition of masking value	63
3.2 Status codes	64
3.3 Constant	65
3.4 Structure.....	73
4. Important Notes	87

3.1.1. Setting of system callback function

```

VOID      ZCLSetCallBack (  PVOID,  Param
                                VOID(CALLBACK* SYSTEMFUNC)( STATUS SYSTEMCODE ,  PVOID ))

```

Argument

PVOID	Param	Value transferred to a callback function
-------	-------	--

VOID(CALLBACK*SYSTEMFUNC)(STATUS SYSTEMCODE,PVOID)

Pointer to callback function

Return value

None

Interpretation

A callback function is set using this function when you want to receive the notification of the system state such as bus reset. To cancel the setting, set NULL to the second parameter.

```
VOID SYSTEMFUNC( STATUS SYSTEMCODE Status, PVOID Context )
```

(ZCLAPI must not be called during processing of a callback function.)

- Event for calling a callback function

- When bus reset is received

Status **STATUSZCL BUSRESET**

Context	Contents set to argument Param of this function
---------	---

- When the sleep state is returned

Status STATUSZCL POWERUP

Context	Contents set to argument Param of this function
---------	---

Example of use

- A callback function is set.

VOID CALLBACK SystemFunc(STATUS_SYSTEMCODE Status, PVOID Context)

```
{
    if( Status == STATUSZCL_BUSRESET )
    {
        //Processing of bus reset
    }

    if( Status == STATUSZCL_POWERUP )
```



```
    {  
        //Processing of sleep cancellation  
    }  
}  
  
if( ZCLSetCallBack( Param, SystemFunc ) )  
{  
    //Succeeds in the setting of a callback function.  
}  
else  
{  
    //Fails in the setting of a callback function.  
}
```

- The setting of a callback function is canceled.

ZCLSetCallBack(NULL, NULL);

3.1.2. Acquisition of error code

STATUS_RTNCODE ZCLGetLastError()

Argument

None

Return value

Error code (See the status code list for details of the error code.)

Interpretation

The error code that was lastly generated is acquired.

See the status code list for details of the error code.

Example of use

- An error code is acquired.

```
STATUS_RTNCODE                      ErrorCode;
```

```
ErrorCode = ZCLGetLastError();
```

3.1.3. Acquisition of connection camera list

BOOL ZCLGetList(ZCL_LIST *List)

Argument

ZCL_LIST	*List	Stores the list of the currently connected cameras. Pointer to a structure
-----------------	--------------	---

Return value

Success TRUE / Failure FALSE

Interpretation

The unique ID names, vender names, and model names of all cameras that are currently connected in a bus are acquired.

Specify the number of arrays in a list for List ->CameraCount.

The number of currently connected cameras is set for restoration when List->CameraCount is "0".

Example of use

- The list of the connected cameras is acquired.

```
ZCL_LIST    *pList;
ULONG       Count;

Count = 0;
if( !ZCLGetList( (pZCL_LIST)&Count ) )
{
    //Fails in the acquisition of a list.
    return;
}
pList = (pZCL_LIST)malloc( sizeof(ZCL_LIST) + sizeof(pList->Info[ 0 ]) * Count );
pList->CameraCount = Count;
if( !ZCLGetList( pList ) )
{
    //Fails in the acquisition of a list.
    return;
}
//Succeeds in the acquisition of a list.
```

3.1.4. Start of camera use

BOOL	ZCLOpen (UINT64	UID,
		HCAMERA	*hCamera)

Argument

UINT64	UID	Unique ID of the camera to be opened
		The camera that is not opened is automatically detected and opened when -1 is specified.
HCAMERA	*hCamera	Pointer for setting a camera handle

Return value

Success TRUE / Failure FALSE

Interpretation

The camera to be used is opened.

A camera handle value is used in each function of ZCL except the function on color conversion.

Be sure to open a camera using **ZCLOpen()** before using each function of ZCL.

During opening, the camera connected in an IEEE1394 bus is automatically recognized for processing by specifying -1 for UID.

Example of use

- A camera is opened.

HCAMERA hCamera;

```
UINT64      UID;
```

UID = -1;

```
if( !ZCLOpen( UID, & hCamera ) )
```

$$\{$$

```
//Processing when a camera cannot be opened
```

```
return;
```

}

3.1.5. Stop of camera use

BOOL ZCLClose(**HCAMERA** hCamera)

Argument

HCAMERA	hCamera	Handle value of the camera to be closed
----------------	---------	---

Return value

Success TRUE / Failure FALSE

Interpretation

The camera opened using **ZCLOpen()** is closed.

Be sure to perform this processing when the use of a camera was stopped.

When the communication with the camera to be treated is done, the use of the camera is stopped after communication processing is stopped.

Be sure to execute this function when it is confirmed that a camera in the open state is not connected.

Example of use

- The opened camera is closed.

```
HCAMERA hCamera;
```

```
ZCLOpen( -1, &hCamera );
```

```
//Processing
```

```
ZCLClose( hCamera );
```

3.1.6. Entire stop of camera use

VOID **ZCLAllClose()**

Argument

None

Return value

None

Interpretation

The use of all opened cameras is stopped.

Example of use

- The use of all opened cameras is stopped.

ZCLAllClose();

3.1.7. Acquisition of camera information

```
BOOL    ZCLCameraInfo( HCAMERA          hCamera,  
                        ZCL_CAMERAINFO    *pInfo,  
                        ZCL_TRANSMITSPEED *pSpeed )
```

Argument

HCAMERA	hCamera	Handle value of the camera to be acquired
ZCL_CAMERAINFO	pInfo	Pointer for setting camera information
ZCL_TRANSMITSPEED	pSpeed	Pointer for setting communication rate information

Return value

Success TRUE / Failure FALSE

Interpretation

Information that a camera has is acquired.

The information is a unique ID name, vender name, model name, and maximum communication-possible rate.

NULL is set to each parameter when no information is required.

Example of use

- Information is acquired.

```
HCAMERA          hCamera;  
ZCL_CAMERAINFO    Info;  
ZCL_TRANSMITSPEED Speed;  
if( ! ZCLCameraInfo( hCamera, &Info, &Speed ) )  
{  
    //Processing when a function failed  
    return;  
}  
  
• A vender name is acquired.  
ZCL_CAMERAINFO    Info;  
if( ! ZCLCameraInfo( hCamera, &Info, NULL ) )  
{  
    //Processing when a function failed  
    return;  
}
```

It is confirmed whether a camera is in the connection state.

Be sure to execute **ZCLClose** when it is confirmed that a camera is not in the connection state.

It is confirmed whether a camera is in the connection state.

Be sure to execute **ZCLClose** when it is confirmed that a camera is not in the connection state.

It is confirmed whether a camera is in the connection state.

Be sure to execute **ZCLClose** when it is confirmed that a camera is not in the connection state.

It is confirmed whether a camera is in the connection state.

Be sure to execute **ZCLClose** when it is confirmed that a camera is not in the connection state.

- The connection state of a camera is confirmed.

It is confirmed whether a camera is in the connection state.

3.1.9. Initialization of camera

BOOL ZCLCameraInit(HCAMERA hCamera)

Argument

HCAMERA	hCamera	Handle value of the camera to be initialized
----------------	---------	--

Return value

Success TRUE / Failure FALSE

Interpretation

A camera is initialized.

A camera is initialized using an initialization register that it has.

The initialized contents vary depending on each camera. For more details, see the camera manual.

Example of use

- A camera is put into the initialization state.

ZCLCameraInit (hCamera);

3.1.10. Confirmation of camera mode

```
BOOL    ZCLCheckCameraMode( HCAMERA          hCamera,
                               ZCL_CAMERAMODE  *Mode )
```

Argument

HCAMERA	hCamera	Handle value of the camera to be confirmed
ZCL_CAMERAMODE	*Mode	Mode value to be confirmed

Return value

Success TRUE / Failure FALSE

Interpretation

The camera mode that a camera has is checked.

A camera has the specified camera mode when the return value is TRUE.

When the return value is FALSE, a camera does not have the specified mode for **ZCLGetLastError()** and **STATUSZCL_NO_SUPPORT**.

Example of use

- The camera mode that a camera has is confirmed.

For standard mode

```
HCAMERA    hCamera;
ZCL_CAMERAMODE  mode;
```

```
mode.StdMode_Flag = TRUE;
mode.u.Std.Mode = ZCL_VGA_YUV1 //640 * 480 YUV411 mode
mode.u.Std.FrameRate = ZCL_Fps_30 //30 frames/s
if( !ZCLCheckCameraMode ( hCamera, &mode ) )
{
    //Processing when no mode exists
    return;
}
```

For extended mode (Format7)

```
HCAMERA    hCamera;
ZCL_CAMERAMODE  mode;
```

```
mode.StdMode_Flag = FALSE;
mode.u.Ext.Mode = ZCL_Mode_0
mode.u.Ext.ColorID = ZCL_MONO
if( !ZCLCheckCameraMode ( hCamera, &mode ) )
{
    //Processing when no mode exists
    return;
}
```

3.1.11. Setting of camera mode

```
BOOL ZCLSetCameraMode( HCAMERA hCamera,
                        ZCL_CAMERAMODE *Mode )
```

Argument

HCAMERA	hCamera	Handle value of the camera to be set
ZCL_CAMERAMODE	*Mode	Camera mode value to be set

Return value

Success TRUE / Failure FALSE

Interpretation

A camera is set to the specified camera mode.

Example of use

- A camera is set to the specified camera mode.

For standard mode

```
HCAMERA hCamera;
ZCL_CAMERAMODE mode;
```

```
mode.StdMode_Flag = TRUE;
mode.u.Std.Mode = ZCL_VGA_YUV1 //640 * 480 YUV411 mode
mode.u.Std.FrameRate = ZCL_Fps_30 //30 frames/s
if( !ZCLSetCameraMode ( hCamera, &mode ) )
{
    //Processing when no mode can be set
    return;
}
```

For extended mode (Format7)

```
HCAMERA hCamera;
ZCL_CAMERAMODE mode;
```

```
mode.StdMode_Flag = FALSE;
mode.u.Ext.Mode = ZCL_Mode_0
```

```
mode.u.Ext.ColorID = ZCL_MONO
if( !ZCLSetCameraMode ( hCamera, &mode ) )
{
    //Processing when no mode can be set
    return;
}
```

3.1.12. Acquisition of camera mode

```
BOOL   ZCLNowCameraMode( HCAMERA          hCamera,  
                           ZCL_CAMERAMODE    *Mode )
```

Argument

HCAMERA	hCamera	Handle value of the camera whose camera mode is acquired
ZCL_CAMERAMODE	*Mode	Pointer for setting the current camera mode value

Return value

Success TRUE / Failure FALSE

Interpretation

The current camera mode of a camera is acquired.

Example of use

- The current camera mode is acquired.

```
HCAMERA          hCamera;  
ZCL_CAMERAMODE    mode;  
  
if( !ZCLNowCameraMode( hCamera , &mode ) )  
{  
    //Processing when failure occurred  
    return;  
}  
if( mode.StdMode_Flag )  
{  
    //Processing in the standard mode  
}  
else  
{  
    //Processing in the extended mode  
}
```

3.1.13. Acquisition of enhancing mode information

```
BOOL  ZCLGetExtModeInfo(  HCAMERA      hCamera,  
                           ZCL_EXTMODEINFO  *pInfo )
```

Argument

HCAMERA	hCamera	Handle value of the camera from which information is acquired
DWORD	Channel	Area where information is set

Return value

Success TRUE / Failure FALSE

Interpretation

Information on the enhancing mode that the camera has is acquired in the batch.

The information is number of mode, number of maximum pixels of each mode, and color coding ID..

Example of use

- Information on the enhancing mode that the camera has is acquired in the batch.

```
HCAMERA      hCamera;  
ZCL_EXTMODEINFO  ExInfo;  
  
if( !ZCLGetExtModeInfo ( hCamera,&ExInfo ) )  
{  
    //Processing when failure occurred  
    return;  
}
```

3.1.14. Saving of memory channel

BOOL **ZCLSaveMem(** **HCAMERA** **hCamera,**
 DWORD **Channel)**

Argument

HCAMERA	hCamera	Handle value of a camera in which a memory channel is saved
DWORD	Channel	Channel number to be specified

Return value

Success TRUE / Failure FALSE

Interpretation

The current status of a camera is saved in a memory channel.

The current camera mode can also be saved depending on the camera.

The channel number is 1 to the maximum channel number. The maximum channel number is acquired using **ZCLCheckFeature**.

Depending on the camera, it may take time to complete saving.

Leave the interval of processing when performing the operation related to a camera after this function is executed.

(See the Users Manual of a camera for more information.)

Example of use

- The current status of a camera is saved in a memory channel.

```
HCAMERA        hCamera;  
  
if( !ZCLSaveMem( hCamera, 2 ) )  
{  
    //Processing when failure occurred  
    return;  
}
```


3.1.15. Read of memory channel

BOOL **ZCLLoadMem**(**HCAMERA** **hCamera**,
 DWORD **Channel**)

Argument

HCAMERA	hCamera	Handle value of a camera in which a memory channel is read
DWORD	Channel	Channel number to be specified

Return value

Success TRUE / Failure FALSE

Interpretation

The camera status and mode saved in the specified memory channel of a camera are read.

The channel number is 0 to the maximum channel number. The maximum channel number is acquired using **ZCLCheckFeature**.

“0” is the factory-setting value of a camera.

Example of use

- The saved camera status and mode are read.

```

HCAMERA        hCamera;

if( !ZCLLoadMem( hCamera, 0 ) )
{
    //Processing when failure occurred
    return;
}
    
```

3.1.16. Confirmation of camera mounting function

```
BOOL   ZCLCheckFeature( HCAMERA           hCamera,  
                        ZCL_CHECKFEATURE *Feature )
```

Argument

HCAMERA	hCamera	Handle value of a camera whose mounting function is confirmed
ZCL_CHECKFEATURE	*Feature	Pointer for setting the information of a mounting function

Return value

Success TRUE / Failure FALSE

Interpretation

The function that a camera mounts is confirmed.

- * The mounting function of a camera varies depending on the camera mode used. Therefore, confirm the camera mounting function again when changing the camera mode.

Example of use

- The mounting function of a camera is confirmed.

```
HCAMERA       hCamera;  
ZCL_CHECKFEATURE   Feature;  
Feature.Version = ZCLGetLibraryRevision();  
Feature.FeatureID = ZCL_BRIGHTNESS;           //Brightness function  
if( !ZCLCheckFeature( hCamera, &Feature ) )  
{  
    //Processing when failure occurred  
    return;  
}  
if( Feature.PresenceFlag )  
{  
    //Processing when a function exists  
}
```

3.1.17. Acquisition of camera parameter value

BOOL	ZCLGetFeatureValue(HCAMERA	hCamera,
	ZCL_GETFEATUREVALUE	*Value)	

Argument

HCAMERA	hCamera	Handle value of a camera in which a camera parameter is acquired
ZCL_GETFEATUREVALUE	*Value	Pointer for setting a camera parameter value

Return value

Success TRUE / Failure FALSE

Interpretation

The value or state of a camera parameter are acquired.

Example of use

- The value and state of brightness are acquired.

HCAMERA	hCamera;
ZCL_GETFEATUREVALUE	Value;

```
Value.Version = ZCLGetLibraryRevision();
Value.FeatureID = ZCL_BRIGHTNESS;
if( !ZCLGetFeatureValue( hCamera, &Value ) )
{
    //Processing when failure occurred
    return;
}
if( Value.u.Std.Auto_M )
{
    //Processing for automatic setting
}
```

- The value and state of WHITEBALANCE are acquired.

HCAMERA	hCamera;
ZCL_GETFEATUREVALUE	Value;

ULONG U, V;
Double K;

```
Value.Version = ZCLGetLibraryRevision();  
Value.FeatureID = ZCL_ WHITEBALANCE;  
if( !ZCLGetFeatureValue( hCamera, &Value ) )  
{  
    //Processing when failure occurred  
    return;  
}  
if( !Value.u.WhiteBalance. Abs )  
{  
    U = Value.u.WhiteBalance.UB_Value;  
    V = Value.u.WhiteBalance.VR_Value  
}  
else  
    K = Value.u.WhiteBalance.Abs_Value;
```

3.1.18. Setting of camera parameter value

```
BOOL ZCLSetFeatureValue ( HCAMERA hCamera,
                           ZCL_SETFEATUREVALUE *Value )
```

Argument

HCAMERA	hCamera	Handle value of a camera in which a camera parameter is set
ZCL_SETFEATUREVALUE	*Value	Contents in which a camera parameter value is set

Return value

Success TRUE / Failure FALSE

Interpretation

A camera parameter is set to the specified value or state.

Example of use

- OnePush of WHITEBALANCE is executed.

```
HCAMERA hCamera;
ZCL_SETFEATUREVALUE Value;

Value.Version = ZCLGetLibraryRevision();
Value.FeatureID = ZCL_WHITEBALANCE;
Value.ReqID = ZCL_ONE_PUSH;
if( !ZCL_SetFeatureValue( hCamera, &Value ) )
{
    //Processing when failure occurred
    return;
}
```

- The automatic and manual modes of a shutter are set.

```
HCAMERA hCamera;
ZCL_SETFEATUREVALUE Value;

Value.Version = ZCLGetLibraryRevision();
Value.FeatureID = ZCL_SHUTTER;
```

```
Value.ReqID = ZCL_AUTO;  
if( !ZCL_SetFeatureValue( hCamera, &Value ) )  
{  
    //Processing when failure occurred  
    return;  
}
```

```
Value.Version = ZCLGetLibraryRevision();  
Value.FeatureID = ZCL_SHUTTER;  
Value.ReqID = ZCL_VALUE;  
Value.u.Std.Value = 1000;  
if( !ZCL_SetFeatureValue( hCamera, &Value ) )  
{  
    //Processing when failure occurred  
    return;  
}
```

```
Value.Version = ZCLGetLibraryRevision();  
Value.FeatureID = ZCL_SHUTTER;  
Value.ReqID = ZCL_ABSVALUE;  
Value.u.Std.Abs_Value = 0.05;  
if( !ZCL_SetFeatureValue( hCamera, &Value ) )  
{  
    //Processing when failure occurred  
    return;  
}
```

- A trigger mode is set and canceled.

```
HCAMERA          hCamera;  
ZCL_SETFEATUREVALUE  Value;
```

```
Value.Version = ZCLGetLibraryRevision();  
Value.FeatureID = ZCL_TRIGGER;  
Value.ReqID = ZCL_VALUE;  
Value.u.Trigger.Polarity = 0;  
Value.u.Trigger.Value = 0;
```

```
Value.u.Trigger.Source = ZCL_Trigger_Source0;  
Value.u.Trigger.Mode = ZCL_Trigger_Mode0;  
Value.u.Trigger.Parameter = 0;  
if( !ZCL_SetFeatureValue( hCamera, &Value ) )  
{  
    //Processing when failure occurred  
    return;  
}  
  
Value.Version = ZCLGetLibraryRevision();  
Value.FeatureID = ZCL_TRIGGER;  
Value.ReqID = ZCL_FEATURE_OFF;  
if( !ZCL_SetFeatureValue( hCamera, &Value ) )  
{  
    //Processing when failure occurred  
    return;  
}
```

3.1.19. Securing of communication resources

BOOL ZCLIsoAlloc(HCAMERA hCamera)

Argument

HCAMERA hCamera Handle value of a camera in which communication resources are secured

Return value

Success TRUE / Failure FALSE

Interpretation

Necessary resources are secured in transferring an image to a camera.

The resources to be secured are the bandwidth and channel number during isochronous transmission.

Before executing this function, a camera mode must be set using **ZCLSetCameraMode()**.

The camera mode is set according to the default value (the current value set in a camera) when it is not set.

The current camera mode can be acquired using **ZCLNowCameraMode()**.

Communication resources may not be able to be secured when they have been secured in the set camera mode or using other cameras.

Be sure to execute **ZCLIsoRelease()** described later and then change the camera mode when a camera mode is changed using **ZCLSetCameraMode()** after this function is executed.

Example of use

- Communication resources are secured.

```
HCAMERA    hCamera;

if( !ZCLIsoAlloc( hCamera ) )
{
    //Processing when resources cannot be secured
    return;
}
```


3.1.20. Release of communication resources

BOOL ZCLIsoRelease(HCAMERA hCamera)

Argument

HCAMERA hCamera Handle value of a camera in which communication resources are released

Return value

Success TRUE / Failure FALSE

Interpretation

The communication resources secured using **ZCLIsoAlloc()** are released.

Example of use

- The communication resources of a camera are released.

HCAMERA hCamera;

ZCLIsoRelease(hCamera);

3.1.21. Start of communication

BOOL ZCLIsoStart(HCAMERA hCamera,
DWORD Frame)

Argument

HCAMERA	hCamera	Handle value of a camera in which communication is started
DWORD	Frame	The number of frames for communication is specified.
	1	: OneShot mode
	2~N	: MultiShot mode
	0	: Free mode (usually during communication) or trigger mode

Return value

Success TRUE / Failure FALSE

Interpretation

The communication with the specified camera is started.

The communication resources of a camera must be secured using **ZCLIsoAlloc()** before executing this function.

Example of use

- Ordinary communication is performed.

```

HCAMERA    hCamera;

if( !ZCLIsoAlloc( hCamera ) )
{
    //Processing when failure occurred
    return;
}
if( !ZCLIsoStart( hCamera, 0 ) )
{
    //Processing when failure occurred
    return;
}

```

- Communication is done in the MultiShot mode. (10-frame reception)

```

ZCLIsoStart( hCamera, 10 );

```

- Communication is done in the OneShot mode.

ZCLIsoStart(hCamera, 1);

3.1.22. Stop of communication

BOOL ZCLIsoStop(**HCAMERA** hCamera)

Argument

HCAMERA hCamera Handle value of a camera in which communication is stopped

Return value

Success TRUE / Failure FALSE

Interpretation

The communication with a camera is stopped.

Communication is stopped even for communication in the MultiShot mode.

Example of use

- The communication with a camera is stopped.

```
HCAMERA hCamera;
```

```
ZCLIsoStop( hCamera );
```

3.1.23. Acquisition of image information

```
BOOL    ZCLGetImageInfo( HCAMERA          hCamera,  
                           ZCL_GETIMAGEINFO *Info )
```

Argument

HCAMERA	hCamera	Handle value of a camera in which image information is acquired
ZCL_GETIMAGEINFO	*Info	Pointer of image information

Return value

Success TRUE / Failure FALSE

Interpretation

The image (image size and image data size) information of a camera is acquired.

Example of use

- Image information is acquired.

```
HCAMERA    hCamera;  
ZCL_GETIMAGEINFO  Info;  
WORD       Width, Height;  
DWORD      Buffer_Len, DataLength;  
ZCL_COLORID    ColorID;  
  
if( !ZCLGetImageInfo( hCamera ) )  
{  
    //Processing when failure occurred  
    return;  
}  
  
Width = Info.Image.Width;  
Height = Info.Image.Height;  
ColorID = Info.Image.ColorID;  
Buffer_Len = Info.Image.Buffer; //Image data length (including a padding byte)  
DataLength = Info.Image.DataLength; //Effective length of image data (not including a padding byte)
```

3.1.24. Setting of image information

```
BOOL    ZCLSetImageInfo( HCAMERA          hCamera,
                           ZCL_SETIMAGEINFO *Info )
```

Argument

HCAMERA	hCamera	Handle value of a camera in which image information is set
ZCL_SETIMAGEINFO	*Info	Image information value to be set

Return value

Success TRUE / Failure FALSE

Interpretation

The image (image size and image position) information of a camera is set.

This function is used to set the information of the image cut off when a camera mode is set to the expansion mode.

An error is restored when a camera mode is set to the standard mode.

Example of use

- The cut-off image in the expansion mode is set.

```
HCAMERA    hCamera;
ZCL_GETIMAGEINFO  GetInfo;
ZCL_SETIMAGEINFO  SetInfo;
ZCL_COLORID       ColorID;
DWORD    Buffer_Len, DataLength;

if( !ZCLGetImageInfo( hCamera, &GetInfo ) )
{
    //Processing when failure occurred
    return;
}

if( GetInfo.StdMode_Flag )
{
    //Processing in the standard mode
    return;
}
```

```
SetInfo.PosX = GetInfo.Ext.UnitPosX * 2;
SetInfo.PosY = GetInfo.Ext.UnitPosY * 5;
SetInfo.Width = GetInfo.Ext.UnitSizeX * 3;
SetInfo.Height = GetInfo.Ext.UnitSizeY * 4;
SetInfo.MaxSize_Flag = false;    //Packet length is set to the minimum value.
if( !ZCLSetImageInfo( hCamera, &SetInfo ) )
{
    //Processing when failure occurred
    return;
}
if( !ZCLGetImageInfo( hCamera, &GetInfo ) )
{
    //Processing when failure occurred
    return;
}
Buffer_Len = GetInfo.Image.Buffer; //Image data length (including a padding byte)
DataLength = GetInfo.Image.DataLength; //Effective length of image data (not including a padding
byte)
ColorID = GetInfo.Image.ColorID;
```

3.1.25. Setting of packet size

```

BOOL    ZCLSetPktSize ( HCAMERA    hCamera,
                           DWORD      Number,
                           DWORD      *pPktLen )

```

Argument

HCAMERA	hCamera	Handle value of a camera in which image information is set
DWORD	Number	Multiple (>2) of the packet length used as standard
DWORD	*pPktLen	Packet length to be set

Return value

Success TRUE / Failure FALSE

Interpretation

This function sets the information of the image cut off when a camera mode is set to the expansion mode and then sets the packet size.

Packet length is specified for the multiple length specified with the minimum packet length, which a camera calculated according to the specified image size, as reference.

Example of use

- Packet size is specified after the cut-off image in the expansion mode is set.

```

HCAMERA    hCamera;
ZCL_GETIMAGEINFO  GetInfo;
ZCL_SETIMAGEINFO   SetInfo;
ZCL_COLORID        ColorID;
DWORD    Buffer_Len, DataLength, PktLen;

if( !ZCLGetImageInfo( hCamera, &GetInfo ) )
{
    //Processing when failure occurred
    return;
}
if( GetInfo.StdMode_Flag )
{
    //Processing in the standard mode

```



```
        return;
    }
    SetInfo.PosX = GetInfo.Ext.UnitPosX * 2;
    SetInfo.PosY = GetInfo.Ext.UnitPosY * 5;
    SetInfo.Width = GetInfo.Ext.UnitSizeX * 3;
    SetInfo.Height = GetInfo.Ext.UnitSizeY * 4;
    SetInfo.MaxSize_Flag = false;    //Packet length is set to the minimum value.
    if( !ZCLSetImageInfo( hCamera, &SetInfo ) )
    {
        //Processing when failure occurred
        return;
    }
    if( !ZCLSetPktSize( hCamera, 3, &PktLen ) )
    {
        //Processing when failure occurred
        return;
    }
    if( !ZCLGetImageInfo( hCamera, &GetInfo ) )
    {
        //Processing when failure occurred
        return;
    }
    Buffer_Len = GetInfo.Image.Buffer;    //Image data length (including a padding byte)
    DataLength = GetInfo.Image.DataLength; //Effective length of image data (not including a padding byte)
    ColorID = GetInfo.Image.ColorID;
```

3.1.26. Acquisition request of image data

```

BOOL    ZCLImageReq(    HCAMERA          hCamera,
                           BYTE            *pBuf,
                           DWORD          Len )

```

Argument

HCAMERA	hcamera	Handle value of a camera in which an image is acquired
BYTE	*pBuf	Pointer of the place where image data is stored
DWORD	Len	Image data buffer length

Return value

Success TRUE / Failure FALSE

Interpretation

Image data is acquired from a camera.

Image data can be acquired proportionally to the number of execution times by executing this function before starting the communication with a camera.

The next frame data is acquired in the course of a frame when this function is executed during communication with a camera.

This function requests the reception of image data. It is immediately restored without waiting that the reception of image data is completed.

Using **ZCLImageCompleteWait** or **ZCLImageCompleteWaitTimeOut** function, confirm that the reception of image data is completed.

Example of use

- Image data is acquired after communication is started.

```

HCAMERA          hCamera;
BYTE            *pData;
ZCL_GETIMAGEINFO Info;

ZCLGetImageInfo( hCamera, &Info );
pData = ( BYTE *)malloc( Info.Image.Buffer );
ZCLIsoStart( hCamera, 0 );
ZCLImageReq( hCamera , pData, Info.Image.Buffer );
ZCLImageCompleteWait( hCamera, pData, 0, 0, 0 );

```

ZCLIsoStop(hCamera);

free(pData);

- Before starting communication, data is acquired after the acquisition of data is set.

HCAMERA hCamera;

BYTE *pData[3];

ZCL_GETIMAGEINFO Info;

int idx;

ZCLGetImageInfo(hCamera, &Info);

for(idx = 0; idx < 3; idx++)

{

 pData[idx] = (BYTE *)malloc(Info.Image.Buffer);

ZCLImageReq(hCamera , pData[idx], Info.Image.Buffer);

}

ZCLIsoStart(hCamera, 0);

for(idx = 0; idx < 3; idx++)

ZCLImageCompleteWait(hCamera, pData[idx], 0, 0, 0);

ZCLIsoStop(hCamera);

for(idx = 0; idx < 3; idx++)

 free(pData[idx]);

3.1.27. Acquisition completion wait of image data

```

BOOL    ZCLImageCompleteWait( HCAMERA          hCamera,
                                   BYTE            *pBuf,
                                   ZCL_TRANSMITSPEED *pSpeed,
                                   DWORD            *pCycleTime,
                                   DWORD            *pCycleCount )

```

Argument

HCAMERA	hCamera	Handle value of a camera by which the completion of data reception is confirmed
BYTE	*pBuf	Pointer of the place where image data is stored
ZCL_TRANSMITSPEED	*pSpeed	Pointer in which a communication rate is stored
DWORD	*pCycleTime	Pointer in which bus time is stored
DWORD	*pCycleCount	Pointer in which a bus count is stored

Return value

Success TRUE / Failure FALSE

Interpretation

It is confirmed by a camera whether the reception of image data was completed.

This function is not restored until the reception completion of image data is confirmed by the specified buffer.

The relevant value is not set when the pointer of the argument such as a communication rate, bus time, and bus count is not set (when NULL is specified).

The bus time is a repetend of 0 to 127. The unit used indicates a second.

The bus count is a repetend of 0 to 7999. It is indicated in units of 125μsec.

Example of use

- The completion of image data is confirmed. The information on communication rate is not used.

```

HCAMERA          hCamera;
BYTE            *pData;
ZCL_GETIMAGEINFO Info;

ZCLGetImageInfo( hCamera, &Info );
pData = ( BYTE *)malloc( Info.Image.Buffer );

```

```
ZCLIsoStart( hCamera, 0 );  
ZCLImageReq( hCamera , pData, Info.Image.Buffer );  
ZCLImageCompleteWait( hCamera, pData, NULL, NULL, NULL );  
ZCLIsoStop( hCamera );  
free( pData );
```

- The completion of image data is confirmed. The information on communication rate is used.

```
HCAMERA          hCamera;  
BYTE             *pData;  
ZCL_GETIMAGEINFO Info;  
ZCL_TRANSMITSPEED Speed;  
DOWRD            CycleTime, CycleCount;
```

```
ZCLGetImageInfo( hCamera, &Info );  
pData = ( BYTE *)malloc( Info.Image.Buffer );  
ZCLIsoStart( hCamera, 0 );  
ZCLImageReq( hCamera , pData, Info.Image.Buffer );  
ZCLImageCompleteWait( hCamera, pData, &Speed, &CycleTime, &CycleCount );  
ZCLIsoStop( hCamera );  
free( pData );
```

3.1.28. Acquisition completion wait of image data (with time-out)

```

BOOL    ZCLImageCompleteWaitTimeOut( HCAMERA          hCamera,
                                           BYTE            *pBuf,
                                           ZCL_TRANSMITSPEED *pSpeed,
                                           DWORD            *pCycleTime,
                                           DWORD            *pCycleCount,
                                           DWORD            Time )

```

Argument

HCAMERA	hCamera	Handle value of a camera by which the completion of data reception is confirmed
BYTE	*pBuf	Pointer of the place where image data is stored
ZCL_TRANSMITSPEED	*pSpeed	Pointer in which a communication rate is stored
DWORD	*pCycleTime	Pointer in which bus time is stored
DWORD	*pCycleCount	Pointer in which a bus count is stored
DWORD	Time	Waiting time, the unit is a millisecond.

Return value

Success TRUE / Failure FALSE

Interpretation

This function is the same function as **ZCLImageCompleteWait** function, and can specify waiting time.

When "0" is specified at waiting time, completion is confirmed , and it returns at once.

When "-1" is specified at waiting time, it becomes the same operation as **ZCLImageCompleteWait** function.

Example of use

- The completion of image data is waited for at 100 millisecond. The information on communication rate is not used.

```

HCAMERA          hCamera;
BYTE            *pData;
ZCL_GETIMAGEINFO Info;

ZCLGetImageInfo( hCamera, &Info );
pData = ( BYTE *)malloc( Info.Image.Buffer );

```

```
ZCLIsoStart( hCamera, 0 );  
ZCLImageReq( hCamera , pData, Info.Image.Buffer );  
if( !ZCLImageCompleteWaitTimeOut( hCamera, pData, NULL, NULL, NULL,100) )  
{  
    //Processing of time-out  
}  
else  
{  
    //Processing of image data acquisition  
}  
ZCLIsoStop( hCamera );  
free( pData );
```

3.1.29. Acquisition cancellation of image data

BOOL ZCLAbortImageReqAll(HCAMERA hCamera)

Argument

HCAMERA	hcamera	Handle value of a camera in which the acquisition of image data is Canceled
----------------	---------	---

Return value

Success TRUE / Failure FALSE

Interpretation

An image acquisition request command executed using **ZCLImageReq()** and a command put into the completion wait state using **ZCLImageCompleteWait()** are canceled.

Example of use

- The image data acquisition command to be requested is canceled.

```
HCAMERA            hCamera;
BYTE               *pData[ 3 ];
ZCL_GETIMAGEINFO   Info;
int                idx;

ZCLGetImageInfo( hCamera, &Info );
for( idx = 0; idx < 3; idx++ )
{
    pData[ idx ] = ( BYTE *)malloc( Info.Image.Buffer );
    ZCLImageReq( hCamera , pData[ idx ], Info.Image.Buffer );
}
ZCLAbortImageReqAll( hCamera );
for( idx = 0; idx < 3; idx++ )
    free( pData[ idx ] );
```


3.1.30. Execution of soft trigger

BOOL ZCLSoftTrigger(HCAMERA hCamera
BOOL OnOff)

Argument

HCAMERA	hcamera	Handle value of a camera in which soft trigger is executed
BOOL	OnOff	On and Off are specified.
	FALSE	Specifies Off.
	TRUE	Specifies On.

Return value

Success TRUE / Failure FALSE

Interpretation

A soft trigger command is issued.

Please execute Off about the soft trigger command after executing On.

However, when trigger mode 0 is set, the library executes Off by the automatic operation.

Example of use

- Soft trigger is issued.

```
HCAMERA                    hCamera;
```

```
ZCLSoftTriger( hCamera, TRUE );
```

```
Sleep( 100 );
```

```
ZCLSoftTriger( hCamera, FALSE );
```

3.1.31. Read of camera control register

```
BOOL    ZCLGetRegister( HCAMERA    hCamera,  
                        ZCL_REGISTER *pReg )
```

Argument

HCAMERA	hcamera	Handle value of a camera in which a register is read
ZCL_REGISTER	*pReg	A register is read. The offset, length, and storage pointer are specified.

Return value

Success TRUE / Failure FALSE

Interpretation

A camera control register is read.

A base address uses the value defined using ConfigROM.

Read length is specified in units of four bytes.

The value to be read corresponds to the contents displayed in DWORD.

The read contents are 0x80020040 when the register value of a camera is 0x80 0x02 0x00 0x40.

Example of use

- A BASIC_FUNC_INQ register is read.

```
HCAMERA    hCamera;  
ZCL_REGISTER  Reg;  
DWORD      RegData;
```

```
Reg.Offset = 0x400;
```

```
Reg.Size = 4;
```

```
Reg.Value = &RegData;
```

```
ZCLGetRegister( hCamera, &Reg );
```

```
// Read in RegData.
```

3.1.32. Read of register

```
BOOL    ZCLGetExtRegister( HCAMERA    hCamera,  
                             ZCL_REGISTER *pReg )
```

Argument

HCAMERA	hcamera	Handle value of a camera in which a register is read
ZCL_REGISTER	*pReg	A register is read. The offset, length, and storage pointer are specified.

Return value

Success TRUE / Failure FALSE

Interpretation

The register of the specified offset address is read.

A base address is 0xfffff000 0000.

Read length is specified in units of four bytes.

The value to be read corresponds to the contents displayed in DWORD.

The read contents are 0x80020040 when the register value of a camera is 0x80 0x02 0x00 0x40.

Example of use

- A Format7 Mode0 Max_IMAGE_SIZE_INQ register is read.

```
HCAMERA    hCamera;  
ZCL_REGISTER    Reg;  
DWORD    Data;
```

```
Reg.Offset = 0x02e0;
```

```
Reg.Size = 4;
```

```
Reg.Value = &Data;
```

```
ZCLGetRegister( hCamera, &Reg );
```

```
Reg.Offset = Data << 2;
```

```
ZCLGetExtRegister( hCamera, &Reg );
```

```
// Read in Data.
```

3.1.33. Write of camera control register

```
BOOL    ZCLSetRegister( HCAMERA    hCamera,  
                        ZCL_REGISTER *pReg )
```

Argument

HCAMERA	hcamera	Handle value of a camera in which a register is written
ZCL_REGISTER	*pReg	A register is written. The offset, length, and data pointer are specified.

Return value

Success TRUE / Failure FALSE

Interpretation

A camera control register is written.

A base address uses the value defined using ConfigROM.

Write length is specified in units of four bytes.

The value to be written corresponds to the contents displayed in DWORD.

The register value of a camera is 0x80 0x02 0x00 0x40 when the write contents are 0x80020040.

Example of use

- The start of image transfer is set to a camera.

```
HCAMERA    hCamera;  
ZCL_REGISTER Reg;  
DWORD      RegData;
```

```
Reg.Offset = 0x614;
```

```
Reg.Size = 4;
```

```
Reg.Value = &RegData;
```

```
RegData = 0x80000000;
```

```
ZCLSetRegister( hCamera, &Reg );
```

3.1.34. Write of register

```
BOOL ZCLSetExtRegister( HCAMERA hCamera,  
                          ZCL_REGISTER *pReg )
```

Argument

HCAMERA	hcamera	Handle value of a camera in which a register is written
ZCL_REGISTER	*pReg	A register is written. The offset, length, and data pointer are specified.

Return value

Success TRUE / Failure FALSE

Interpretation

The register of the specified offset address is written.

A base address is 0xfffff000 0000.

Write length is specified in units of four bytes.

The value to be written corresponds to the contents displayed in DWORD.

The register value of a camera is 0x80 0x02 0x00 0x40 when the write contents are 0x80020040.

Example of use

- MONO16 is specified in a Format7 Mode0 COLOR_CODING_ID register.

```
HCAMERA          hCamera;  
ZCL_REGISTER    Reg;  
DWORD           Data;
```

```
Reg.Offset = 0x02e0;
```

```
Reg.Size = 4;
```

```
Reg.Value = &Data;
```

```
ZCLGetRegister( hCamera, &Reg );
```

```
Reg.Offset = ( Data << 2 ) + 0x010;
```

```
Data = 5 << 24;
```

```
ZCLSetExtRegister( hCamera, &Reg );
```

3.1.35. Acquisition of library revision

DWORD **ZCLGetLibraryRevision()**

Argument

None

Return value

Library revision number

Interpretation

The revision number of a library is acquired.

In version 1.20, the revision number is 120.

The revision number is changed and updated when addition (or change) occurs in the mounted function.

Example of use

- A version is acquired.

```
if( ZCLGetLibraryRevision() == 120 )  
{  
    //For a version of 1.20  
}  
else  
{  
    //For versions other than 1.20  
}
```

3.1.36. Reinitialization of isochronous resources

BOOL ZCLReset(void)

Argument

None

Return value

Success TRUE / Failure FALSE

Interpretation

Isochronous resources are reinitialized.

* Usually, do not use this function.

Example of use

ZCLReset();

3.1.37. Creation of color conversion table

```
BOOL    ZCLCreateConvHandle ( HCTBL                *hTbl,
                                ZCL_CONVERTMODE Mode,
                                ZCL_SHIFTID      Shift,
                                ZCL_COLORVALUE   *pValue )
```

Argument

HCTBL	*hTbl	Pointer for setting a color conversion handle
ZCL_CONVERTMODE	Mode	A conversion mode is set.
ZCL_SHIFTID	Shift	A bit shift is specified.
ZCL_COLORVALUE	*pValue	A color conversion coefficient is specified.

Return value

Success TRUE / Failure FALSE

Interpretation

The resources for converting in the mode in which the image data sent from a camera was specified are created.

32-bit, 24-bit, 16-bit, 15-bit, and color filter (RAW8 and RAW16) color conversion modes are specified for conversion mode.

The conversion mode is fixed to 32-bit color when a color filter is specified.

For the specification of a bit shift, the bit to be selected is specified when image data is eight-bit gradation and above.

For a color conversion coefficient, the coefficient during color conversion from YUV information to RGB information is specified. The coefficient is specified using the expression below.

$$R = Y + pValue \rightarrow a \times V$$

$$G = Y - pValue \rightarrow b \times V - pValue \rightarrow c \times U$$

$$B = Y + pValue \rightarrow d \times U$$

When no coefficient is specified (NULL is set to pValue), color conversion is done as standard by the expression below.

$$pValue \rightarrow a = 1.402$$

$$pValue \rightarrow b = 0.711$$

$$pValue \rightarrow c = 0.343$$

$$pValue \rightarrow d = 1.772$$

Example of use

- A color conversion coefficient performs 24-bit color conversion as a standard value.

```
HCTBL          hTbl;
```

```
ZCLCreateConvHandle ( & hTbl, ZCL_C24bit, ZCL_SFT0, NULL );
```

- A color conversion coefficient is set to a = 1.5, b = 0.8, c = 0.4, and d = 1.9 so as to perform 24-bit color conversion.

```
HCTBL          hTbl;
```

```
ZCL_COLORVALUE      Value;
```

```
Value.a = 1.5;
```

```
Value.b = 0.8;
```

```
Value.c = 0.4;
```

```
Value.d = 1.9;
```

```
ZCLCreateConvHandle ( & hTbl, ZCL_C24bit, ZCL_SFT0, &Value );
```

3.1.38. Opening of color conversion table

VOID ZCLCloseConvHandle(HCTBL hTbl)

Argument

HCTBL hTbl Handle value of the color conversion table to be opened

Return value

None

Interpretation

The table created using **ZCLCreateConvHandle()** is opened.

Example of use

- A color conversion table is opened.

HCTBL hTbl;

ZCLCloseConvHandle(hTbl);

3.1.39. Entire opening of color conversion table

VOID ZCLCloseAllConvHandle()

Argument

None

Return value

None

Interpretation

All tables created using **ZCLCreateConvHandle()** are opened.

Example of use

- All color conversion tables are opened.

ZCLCloseAllConvHandle();

3.1.40. Execution of color conversion

```

BOOL    ZCLColorConvExec ( HCTBL          hTbl,
                               DWORD         Width,
                               DWORD         Height,
                               ZCL_COLORMODE *pMode,
                               BYTE          *SrcBuf,
                               BYTE          *DstBuf )

```

Argument

HCTBL	hTbl	Handle value of the color conversion table to be opened
DWORD	Width	Width of image
DWORD	Height	Height of image
ZCL_COLORMODE	*pMode	Conversion information Color identification of original data Identification of color filter Data array after conversion
BYTE	*SrcBuf	Buffer pointer in which conversion source image data is stored
BYTE	*DstBuf	Buffer pointer in which the converted image data is stored

Return value

Success TRUE / Failure FALSE

Interpretation

Color conversion is executed.

When **ZCL_BMPmode** is specified by specifying the data array after conversion, the number of bytes in one line is automatically adjusted to a four-byte boundary if it is not a four-byte boundary.

Example of use

- The array after conversion is reversed at top and bottom for color conversion.

```

BYTE    Data[ 20 * 20 ];
BYTE    BMP[ 20 * 20 * 3 ];
ZCL_COLORMODE Mode;
HCTBL    hTbl;

Mode.ColorID = ZCL_YUV422;

```

Mode.Cfilter = 0;

Mode.StoreMode = **ZCL_BMPmode**;

ZCLColorConvExec(hTbl, 20, 20, &Mode, &Data[0], &BMP[0]);

- Color conversion is executed.

BYTE Data[20 * 20];

BYTE BMP[20 * 20 * 3];

ZCL_COLORMODE Mode;

HCTBL hTbl;

Mode.ColorID = **ZCL_YUV422**;

Mode.Cfilter = 0;

Mode.StoreMode = **ZCL_MEMmode**;

ZCLColorConvExec(hTbl, 20, 20, &Mode, &Data[0], &BMP[0]);

3.1.41. Setting of BITMAPINFO information

```
BOOL ZCLColorConvSetBMPINFO ( HCTBL hTbl,
                                DWORD Width,
                                DWORD Height,
                                BITMAPINFO *pBmpInfo )
```

Argument

HCTBL	hTbl	Handle value of the color conversion table to be opened
DWORD	Width	Width of image
DWORD	Height	Height of image
BITMAPINFO	*pBmpInfo	BMPINFO information table

Return value

Success TRUE / Failure FALSE

Interpretation

The BITMAPINFO information when converting into a BMP format during color conversion is set.

Example of use

- BITMAPINFO information is set.

```
BITMAPINFO BmpInfo;
```

```
HCTBL hTbl;
```

```
ZCLColorConvSetBMPINFO ( hTbl, 20, 20, & BmpInfo );
```

3.1.42. Confirmation of Hitachi Kokusai camera model

BOOL **ZCLCheckHitachi** (**HCAMERA** **hCamera**,)

Argument

HCAMERA	hCamera	Handle value of a camera in which a Hitachi Kokusai camera model is confirmed
----------------	---------	---

Return value

Success TRUE / Failure FALSE

Interpretation

This function must be called once when the vender unique function of a camera made by Hitachi Kokusai is used.

The functions below can be used after this function is called.

ZCLHMaskingOn()

ZCLHMaskingOff()

ZCLGetHMasking()

Example of use

- The use of a new expanded function made by Hitachi Kokusai is declared.

HCAMERA	hCamera;
----------------	----------

ZCLCheckHitachi(hCamera);

3.1.43. Setting of masking

```
BOOL    ZCLHMaskingOn(  HCAMERA    hCamera  
                                ZCL_HMASKING    *pMasking )
```

Argument

HCAMERA	hCamera	Handle value of a camera in which masking is set
ZCL_HMASKING	pMasking	Masking value to be set

Return value

Success TRUE / Failure FALSE

Interpretation

A masking value is set for each color.

Example of use

- A masking value is set.

```
HCAMERA                hCamera;  
ZCL_HMASKING          Masking;
```

```
Masking.Saturaton.R = 0x80;
```

```
Masking.Saturaton.G = 0x80;
```

```
Masking.Saturaton.B = 0x80;
```

```
Masking.Saturaton.Y = 0x80;
```

```
Masking.Saturaton.C = 0x80;
```

```
Masking.Saturaton.M = 0x80;
```

```
Masking. Hue.R = 0x80;
```

```
Masking. Hue.G = 0x80;
```

```
Masking. Hue.B = 0x80;
```

```
Masking. Hue.Y = 0x80;
```

```
Masking. Hue.C = 0x80;
```

```
Masking. Hue.M = 0x80;
```

```
ZCLHMaskingOn( hCamera, &Masking );
```


3.1.44. Release of masking setting

BOOL ZCLHMaskingOff(HCAMERA hCamera)

Argument

HCAMERA	hCamera	Handle value of a camera in which the setting of masking is released
----------------	---------	--

Return value

Success TRUE / Failure FALSE

Interpretation

A masking function is released.

Example of use

- A masking function is released.

HCAMERA hCamera;

ZCLHMaskingOff (hCamera);

3.1.45. Acquisition of masking value

```

BOOL ZCLGetHMasking( HCAMERA hCamera,
                        BOOL *pOnOff,
                        ZCL_HMASKING *pMasking )

```

Argument

HCAMERA	hCamera	Handle value of a camera in which a masking value is acquired
BOOL	pOnOff	Masking function state 0 Invalid 1 Valid
ZCL_HMASKING	pMasking	Current setting value

Return value

Success TRUE / Failure FALSE

Interpretation

The current setting value of masking is acquired.

Example of use

- A masking value is acquired.

```

HCAMERA hCamera;
BOOL OnOff;
ZCL_HMASKING Masking;

ZCLGetHMasking ( hCamera, &OnOff, &Masking );

```

3.2 Status codes

STATUSZCL_NO_ERROR	No error
STATUSZCL_COMPLETE	Success in processing
STATUSZCL_PARAMETER_ERROR	A parameter is illegal.
STATUSZCL_BUFFER_SHORT	A buffer is short.
STATUSZCL_OPEN_ERROR	Failure in the opening of a camera
STATUSZCL_OPENED	A camera has been already opened.
STATUSZCL_CANNOT_FOUND	A camera cannot be found.
STATUSZCL_NO_OPEN	A camera is not opened.
STATUSZCL_COMMUNICATE_ERROR	Failure in communication
STATUSZCL_DATA_INACCURACY	The acquired data is inaccurate.
STATUSZCL_NO_SUPPORT	No function is mounted.
STATUSZCL_VMODE_ERROR	Camera parameter setting error
STATUSZCL_FEATURE_ERROR	Camera feature control error
STATUSZCL_VALUE_ERROR	Camera parameter setting error
STATUSZCL_SELFCLEAR_ERROR	A self-clear flag is not cleared.
STATUSZCL_IMAGE_ERROR	Image size setting error
STATUSZCL_RESOURCE_ERROR	Requested. during securing of isochronous resources
STATUSZCL_NOTRESOURCE_ERROR	Isochronous resources are not secured.
STATUSZCL_ALLOCATE_ERROR	Failure in the securing of isochronous resources
STATUSZCL_STARTED_ERROR	The start state has been already reached.
STATUSZCL_NOTSTART_ERROR	The start state is not reached.
STATUSZCL_REQUEST_ERROR	Failure in image request
STATUSZCL_REQUEST_TIMEOUT	Time-out in image request
STATUSZCL_SOFTTRIGGER_BUSY	During soft trigger execution
STATUSZCL_MULTISLOPE_ERROR	Multi-slope setting error
STATUSZCL_UNDEF_ERROR	Other errors

3.3 Constant

Mode of standard format

typedef enum

```
{  
    ZCL_QQVGA          = 0,      // 160 x 120 YUV(4:4:4)  
    ZCL_QVGA,           // 320 x 240 YUV(4:2:2)  
    ZCL_VGA_YUV1,       // 640 x 480 YUV(4:1:1)  
    ZCL_VGA_YUV2,       // 640 x 480 YUV(4:2:2)  
    ZCL_VGA_RGB,        // 640 x 480 RGB  
    ZCL_VGA_MONO,       // 640 x 480 Mono  
    ZCL_VGA_MONO16,     // 640 x 480 Mono16  
    ZCL_SVGA_YUV,       // 800 x 600 YUV(4:2:2)  
    ZCL_SVGA_RGB,       // 800 x 600 RGB  
    ZCL_SVGA_MONO,     // 800 x 600 MONO  
    ZCL_SVGA_MONO16,    // 800 x 600 MONO16  
    ZCL_XGA_YUV,        // 1024 x 768 YUV(4:2:2)  
    ZCL_XGA_RGB,        // 1024 x 768 RGB  
    ZCL_XGA_MONO,       // 1024 x 768 MONO  
    ZCL_XGA_MONO16,     // 1024 x 768 MONO16  
    ZCL_SXGA_YUV,       // 1280 x 960 YUV(4:2:2)  
    ZCL_SXGA_RGB,       // 1280 x 960 RGB  
    ZCL_SXGA_MONO,     // 1280 x 960 MONO  
    ZCL_SXGA_MONO16,    // 1280 x 960 MONO16  
    ZCL_UXGA_YUV,       // 1600 x 1200 YUV(4:2:2)  
    ZCL_UXGA_RGB,       // 1600 x 1200 RGB  
    ZCL_UXGA_MONO,     // 1600 x 1200 MONO  
    ZCL_UXGA_MONO16,    // 1600 x 1200 MONO16  
} ZCL_STDMODE;
```

Frame rate of standard format

```
typedef enum
{
    ZCL_Fps_1875          = 0,      // 1.875fps
    ZCL_Fps_375,          // 3.75fps
    ZCL_Fps_75,           // 7.5fps
    ZCL_Fps_15,           // 15fps
    ZCL_Fps_30,           // 30fps
    ZCL_Fps_60,           // 60fps
    ZCL_Fps_120,          // 120fps
    ZCL_Fps_240           // 240fps
} ZCL_FPS;
```

Mode of extended format

```
typedef enum
{
    ZCL_Mode_0            = 0,      // Mode_0
    ZCL_Mode_1,           // Mode_1
    ZCL_Mode_2,           // Mode_2
    ZCL_Mode_3,           // Mode_3
    ZCL_Mode_4,           // Mode_4
    ZCL_Mode_5,           // Mode_5
    ZCL_Mode_6,           // Mode_6
    ZCL_Mode_7            // Mode_7
} ZCL_EXTMODE;
```

```
Color coding ID
typedef enum
{
    ZCL_MONO                = 0,        // MONO 8bit
    ZCL_YUV411,              // YUV411 8bit
    ZCL_YUV422,              // YUV422 8bit
    ZCL_YUV444,              // YUV444 8bit
    ZCL_RGB,                 // RGB 8bit
    ZCL_MONO16,              // MONO16 16bit
    ZCL_RGB16,               // RGB16 16bit
    ZCL_SMONO16,             // Signed MONO16 16bit
    ZCL_SRGB16,              // Signed RGB16 16bit
    ZCL_RAW,                 // RAW 8bit
    ZCL_RAW16,               // RAW16 16bit
} ZCL_COLORID;
```

```

Function code
typedef enum
{
    ZCL_BRIGHTNESS          = 0,      // Brightness
    ZCL_AE,                  // Auto Exposure
    ZCL_SHARPNESS,           // Sharpness
    ZCL_WHITEBALANCE,        // White Balance
    ZCL_HUE,                 // HUE
    ZCL_SATURATION,          // Saturation
    ZCL_GAMMA,               // Gamma
    ZCL_SHUTTER,             // Shutter
    ZCL_GAIN,                // Gain
    ZCL_IRIS,                // Iris
    ZCL_FOCUS,               // Focus
    ZCL_TEMPERATURE,         // Temperature
    ZCL_TRIGGER,             // Trigger
    ZCL_TRIGGER_DELAY,       // Trigger Delay
    ZCL_WHITE_SHADING,       // White Shading
    ZCL_FRAMERATE,           // FrameRate
    ZCL_ZOOM,                // Zoom
    ZCL_PAN,                 // Pan
    ZCL_TILT,                // Tilt
    ZCL_OPTICAL_FILTER,      // Optical Filter
    ZCL_ONE_SHOT,            // One Shot
    ZCL_MULTI_SHOT,          // Multi Shot
    ZCL_POWER_ONOFF,         // Power On Off
    ZCL_MEMORYCHANNEL        // Memory Channel
} ZCL_FEATUREID;

```

Trigger mode

```
typedef enum
{
    ZCL_Trigger_Mode0          = 0,      // Trigger Mode0
    ZCL_Trigger_Mode1,          // Trigger Mode1
    ZCL_Trigger_Mode2,          // Trigger Mode2
    ZCL_Trigger_Mode3,          // Trigger Mode3
    ZCL_Trigger_Mode4,          // Trigger Mode4
    ZCL_Trigger_Mode5,          // Trigger Mode5
    ZCL_Trigger_Mode14         = 14,     // Trigger Mode14
    ZCL_Trigger_Mode15         // Trigger Mode15
} ZCL_TRIGGERMODE;
```

Trigger source code

```
typedef enum
{
    ZCL_Trigger_Source0        = 0,      // Trigger Source0
    ZCL_Trigger_Source1,        // Trigger Source1
    ZCL_Trigger_Source2,        // Trigger Source2
    ZCL_Trigger_Source3,        // Trigger Source3
    ZCL_Software_Trigger        = 7      // Software Trigger
} ZCL_TRIGGERSOURCE;
```


Color conversion code

typedef enum

```
{  
    ZCL_C24bit          = 0,      // 24bit Color conversion  
    ZCL_C16bit,          // 16bit Color conversion  
    ZCL_C15bit,          // 15bit Color conversion  
    ZCL_CFilter,         // No 32Bit color conversion correction of the RAW data  
    ZCL_C32bit,          // 32bit Color conversion  
    ZCL_CFilterRAW8G,    // 32Bit color conversion correction of the RAW data  
    ZCL_CFilterRAW16,    // No 32Bit color conversion correction of the RAW16  
    data ZCL_CFilterRAW16G, // 32Bit color conversion correction of the RAW16 data  
    ZCL_CFilterRAW8 = ZCL_Cfilter // No 32Bit color conversion correction of the RAW data  
} ZCL_CONVERTMODE;
```

Row of data of RAW data

typedef enum

```
{  
    ZCL_FGBRG          = 0,      // GB/RG  
    ZCL_FRGGB,          // RG/GB  
    ZCL_FBGGR,          // BG/GR  
    ZCL_FGRBG,          // GR/BG  
} ZCL_CFILTERMODE;
```

Specification of selection of effective bit

```
typedef enum
{
    ZCL_SFT0          = 0,      // Subordinate position 7-0 bit
    ZCL_SFT1,              // Subordinate position 8-1 bit
    ZCL_SFT2,              // Subordinate position 9-2 bit
    ZCL_SFT3,              // Subordinate position 10-3 bit
    ZCL_SFT4,              // Subordinate position 11-4 bit
    ZCL_SFT5,              // Subordinate position 12-5 bit
    ZCL_SFT6,              // Subordinate position 13-6 bit
    ZCL_SFT7,              // Subordinate position 14-7 bit
    ZCL_SFT8              // Subordinate position 15-8 bit
} ZCL_SHIFTID;
```

Coordinates specification after color is converted

```
typedef enum
{
    ZCL_BMPmode        = 0,      // BMP file mode
    ZCL_MEMmode         // MEMORY mode
} ZCL_STOREMODE;
```

Request code of function setting

```
typedef enum
{
    ZCL_FEATURE_OFF     = 0,      // Feature function stop
    ZCL_ONE_PUSH,         // Execution of One Push
    ZCL_AUTO,             // Automatic setting
    ZCL_VALUE,            // Manual value setting
    ZCL_ABSVALUE         // ABS manual value setting
} ZCL_SETREQID;
```

Status code of system call back

```
typedef enum
{
    STATUSZCL_BUSRESET          = 1,      // Bus reset generation
    STATUSZCL_POWERUP           // Return from sleep of system
} STATUS_SYSTEMCODE;
```

3.4 Structure

Camera information

typedef struct

```
{
    UINT64          UID;                // GUID
    BYTE            VendorName[ 256 ];  // Vendor name
    BYTE            ModelName[ 256 ];   // Model name
} ZCL_CAMERAINFO, *pZCL_CAMERAINFO;
```

Camera information list

typedef struct

```
{
    DWORD           CameraCount;        // Number of connected cameras or
                                         numbers of Info arrays
    ZCL_CAMERAINFO  Info[ 0 ];         // Camera information
} ZCL_LIST, *pZCL_LIST;
```

CameraCount The number of ZCL_CAMERAINFO is specified before the request is issued.
After the request is executed, the number of a number of connected cameras and effective ZCL_CAMERAINFO is set.

Camera mode setting

typedef struct

```
{
    BOOL                                StdMode_Flag;        // Standard mode flag
    union
    {
        //          Standard mode
        struct
        {
            ZCL_STDMODE                Mode;                // Mode
            ZCL_FPS                     FrameRate;           // Frame rate
        } Std;

        //          Enhancing mode
        struct
        {
            ZCL_EXTMODE                 Mode;                // Mode
            ZCL_COLORID                 ColorID;             // Color coding ID
            ZCL_CFILTERMODE             FilterID;            // Row of data of RAW data
        } Ext;
    } u;
} ZCL_CAMERAMODE, *pZCL_CAMERAMODE;
```

StdMode_Flag It is shown whether to use the Std definition or the Ext definition.

Enhancing mode information

typedef struct

{

 DWORD ModeCount; // Number of enhancing modes

 struct

 {

 WORD MaxWidth; // The maximum width size

 WORD MaxHeight; // The maximum height size

 WORD C_MONO:1; // It has the function in "1".

 Hereafter, it is the same to C_RAW16.

 WORD C_YUV411:1;

 WORD C_YUV422:1;

 WORD C_YUV444:1;

 WORD C_RGB:1;

 WORD C_MONO16:1;

 WORD C_RGB16:1;

 WORD C_SMONO16:1;

 WORD C_SRGB16:1;

 WORD C_RAW:1;

 WORD C_RAW16:1;

 } Mode[8];

} ZCL_EXTMODEINFO, *pZCL_EXTMODEINFO;

ModeCount An effective number of Mode is shown.

Mounting function information

typedef struct

```
{
    DWORD          Version;
    ZCL_FEATUREID  FeatureID;
    BOOL           PresenceFlag;
    union
    {
        //    Function commonness definition
        struct
        {
            BYTE      Abs_Inq:1;      // Capability of control with absolute value
            BYTE      One_Push_Inq:1; // One Push auto mode
            BYTE      ReadOut_Inq:1;  // Capability of reading the value of this feature
            BYTE      On_Off_Inq:1;   // Capability of switching this feature On and Off
            BYTE      Auto_Inq:1;     // Auto mode
            BYTE      Manual_Inq:1;   // Manual mode
            WORD      Min_Value;      // Minimum value for this feature control
            WORD      Max_Value;      // Maximum value for this feature control
            float      Abs_Min_Value; // Absolute minimum value for this feature control
            float      Abs_Max_Value; // Absolute maximum value for this feature control
        } Std;

        //    Trigger
        struct
        {
            BYTE      Abs_Inq:1;
            BYTE      ReadOut_Inq:1;
            BYTE      On_Off_Inq:1;
            BYTE      Polarity_Inq:1; // Capability of changing polarity
            BYTE      Value_Read_Inq:1; // Terminal state input function
            BYTE      Source0:1;      // Input source division
            BYTE      Source1:1;
            BYTE      Source2:1;
        }
    }
};
```

```

        BYTE        Source3:1;
        BYTE        Software:1;          // Software trigger function
        BYTE        Mode0:1;             // Mode division
        BYTE        Mode1:1;
        BYTE        Mode2:1;
        BYTE        Mode3:1;
        BYTE        Mode4:1;
        BYTE        Mode5:1;
        BYTE        Mode14:1;
        BYTE        Mode15:1;
        float        Abs_Min_Value;      // Absolute minimum value for this feature control
        float        Abs_Max_Value;      // Absolute minimum value for this feature control
    } Trigger;
    BYTE            Max_MemChannel; // The maximum memory channel number
} u;
} ZCL_CHECKFEATURE, *pZCL_CHECKFEATURE;

Version            The version of a present library is set.
FeatureID          The function code in which it wants to check the content of the function is set.
PresenceFlag       The presence of the function is set.

As for Trigger, information is set to the Trigger definition.
As for the maximum memory channel, information is set to Max_MemChannel.
Additionally, information is set to the Std definition.

```


Acquisition of camera parameter value

```
typedef struct
{
    DWORD Version;
    ZCL_FEATUREID FeatureID;

    union
    {
        // Function commonness definition
        struct
        {
            BYTE Abs:1; // Absolute value selection
            BYTE On_Off:1; // Function effective/invalidity
            BYTE Auto_M:1; // State of automatic / Manual operation
            WORD Value; // Present value
            float Abs_Value; // Present absolute value
        } Std;

        // WhiteBalance
        struct
        {
            BYTE Abs:1;
            BYTE On_Off:1;
            BYTE Auto_M:1;
            WORD UB_Value; // Present value of UB
            WORD VR_Value; // Present value of VR
            float Abs_Value;
        } WhiteBalance;

        // Temperature
        struct
        {
            BYTE Abs:1;
            BYTE On_Off:1;
            BYTE Auto_M:1;
        } Temperature;
    }
};
```

```

        WORD            Target_Value;
        WORD            Temp_Value;
        float           Abs_Value;
    } Temperature;

//    Trigger
struct
{
    BYTE               Abs:1;
    BYTE               On_Off:1;
    BYTE               Rcvd:1;
    BYTE               Polarity:1;    // Input polarity
    BYTE               Value:1;       // Input value of present
    BYTE               Source;        // Present source
    BYTE               Mode;          // Present mode
    WORD               Parameter;
    float              Abs_Value;
} Trigger;

//    TriggerDelay
struct
{
    BYTE               Abs:1;
    BYTE               On_Off:1;
    BYTE               Rcvd:1;
    WORD               Value;
    float              Abs_Value;
} TriggerDelay;

//    WhiteShading
struct
{
    BYTE               Abs:1;
    BYTE               On_Off:1;
    BYTE               Auto_M:1;
    BYTE               R_Value;

```

```

        BYTE          G_Value;
        BYTE          B_Value;
        float         Abs_Value;
    } WhiteShading;

    BOOL              Exec_Flag;
    BOOL              PowerOn_Flag;
} u;
} ZCL_GETFEATUREVALUE, *pZCL_GETFEATUREVALUE;
Version              The version of a present library is set.
FeatureID            The function code in which it wants to acquire a present camera parameter value
                     is set.

As for WhiteBalance, information is set to the WhiteBalance definition.
As for Temperature, information is set to the Temperature definition.
As for Trigger, information is set to the Trigger definition.
As for TriggerDelay, information is set to the TriggerDelay definition.
As for WhiteShading, information is set to the WhiteShading definition.
As for s tate of power supply, information is set to the PowerOn_Flag.
As for Multi-shot and One-shot running state, information is set to the Exec_Flag.
Additionally, a present content is set to the Std definition.

```

Setting of camera parameter value

```
typedef struct
{
    DWORD Version;
    ZCL_SETREQID ReqID;
    ZCL_FEATUREID FeatureID;

    union
    {
        // Function commonness definition
        struct
        {
            WORD Value;
            float Abs_Value;
        } Std;

        // WhiteBalance
        struct
        {
            WORD UB_Value;
            WORD VR_Value;
            float Abs_Value;
        } WhiteBalance;

        // Temperature
        struct
        {
            WORD Target;
            WORD Temp;
            float Abs_Value;
        } Temperature;

        // Trigger
        struct
        {
```

```

        BYTE          Polarity:1;
        BYTE          Value:1;
        BYTE          Source;
        BYTE          Mode;
        WORD          Parameter;
        float         Abs_Value;
    } Trigger;

    //          WhiteShading
    struct
    {
        BYTE          R_Value;
        BYTE          G_Value;
        BYTE          B_Value;
        float         Abs_Value;
    } WhiteShading;
} u;
} ZCL_SETFEATUREVALUE, *pZCL_SETFEATUREVALUE;

Version          The version of a present library is set.
ReqID            The request code is set.
FeatureID        The function code in which it wants to set the camera parameter value is set.
As for WhiteBalance, information is set to the WhiteBalance definition.
As for Temperature, information is set to the Temperature definition.
As for Trigger, information is set to the Trigger definition.
As for WhiteShading, information is set to the WhiteShading definition.
Additionally, the content that the Std definition demands is set.

```

```

    Image information
typedef      struct
{
    BOOL      StdMode_Flag;
    struct
    {
        WORD      PosX;      // Present image start position X
        WORD      PosY;      // Present image start position Y
        WORD      Width;     // Present width of image
        WORD      Height;    // Present height of image
        ZCL_COLORID      ColorID;    // Present color coding ID
        DWORD      DataLength;    // Effective data length of image data
        DWORD      Buffer;        // Necessary buffer length for image data
                                reception
    } Image;

    struct
    {
        WORD      MaxImageX;    // The maximum image width size
        WORD      MaxImageY;    // The maximum image height size
        WORD      UnitSizeX;    // Width of cutting out unit
        WORD      UnitSizeY;    // Height of cutting out unit
        WORD      UnitPosX;    // Width of cutting out boundary
        WORD      UnitPosY;    // Height of cutting out boundary
    } Ext;
} ZCL_GETIMAGEINFO, *pZCL_GETIMAGEINFO;

StdMode_Flag      The effectiveness of the Ext definition is set.

                  Information is set to the Ext definition, when the camera is set to
                  the enhancing mode.

```

Specification of image information

```
typedef      struct
{
    WORD      PosX;           // Image start position X
    WORD      PosY;           // Image start position Y
    WORD      Width;          // Width of image
    WORD      Height;         // Height of image
    BOOL      MaxSize_Flag;
} ZCL_SETIMAGEINFO, *pZCL_SETIMAGEINFO;
```

MaxSize_Flag A maximum size and a minimum size of the size of the packet in the image forwarding are selected.

Maximum size TRUE / Minimum size FALSE

Register information

```
typedef      struct
{
    DWORD      Offset;
    DWORD      Size;
    PVOID      Value;
} ZCL_REGISTER, *pZCL_REGISTER;
```

Offset The Offset position from the base is specified.

Size The request size in the setting and reading is specified.

Value The area of the setting and reading is specified.

Color conversion constant

```
typedef      struct
{
    double a;
    double b;
    double c;
    double d;
} ZCL_COLORVALUE, *pZCL_COLORVALUE;
```

Color conversion execution parameter

```
typedef      struct
{
    ZCL_COLORID      ColorID;
    ZCL_CFILTERMODE   CFilter;
    ZCL_STOREMODE     StoreMode;
} ZCL_COLORMODE, *pZCL_COLORMODE;
```

ColorID Color coding ID of the image data is set.

CFilter When the image data is RAW data, the row and the correction, etc. of data are specified.

StoreMode The arrangement of the data after the color is converted is specified.

The structure shown after this is for a peculiar function of Hitachi Kokusai camera.

```
Color information
typedef      struct
{
    BYTE      R;
    BYTE      G;
    BYTE      B;
    BYTE      Y;
    BYTE      C;
    BYTE      M;
} ZCL_HITACHICOLOR, *pZCL_HITACHICOLOR
```

```
Masking information
typedef      struct
{
    ZCL_HITACHICOLOR    Saturation;
    ZCL_HITACHICOLOR    Hue;
} ZCL_HMASKING, *pZCL_HMASKING;
```

4. Important Notes

4.1. Flow of Basic Operation

- **Start of camera use**

1. Open a camera using **ZCLOpen()**.

- **Preparation of communication**

1. Set the camera mode and frame rate using **ZCLSetMode()**. (Can be omitted.)
2. Investigate the function installed in a camera using **ZCLCheckFeature()**. (Can be omitted.)
3. Set the required parameter using **ZCLSetFeatureValue()**. (Can be omitted.)
4. Acquire the buffer size for image data read using **ZCLGetImageInfo()**.
5. Prepare the start of communication using **ZCLIsoAlloc()**.

- **Start of communication**

1. Start communication using **ZCLIsoStart()**.
2. Request the acquisition of image data using **ZCLImageReq()**.
3. Confirm using **ZCLImageCompleteWait()** that the acquisition of image data is completed.
4. Repeat steps 2 and 3 as required.

- **Stop of communication**

1. Stop communication using **ZCLIsoStop()**.
2. Cancel the request of image data acquisition, which is not completed, using **ZCLAbortImageReqAll()**.

- **Release of communication preparation**

1. Release the preparation of communication using **ZCLIsoRelease()**.

- **Stop of camera use**

1. Close a camera (release a camera from a library) using **ZCLClose()**.

- * Caution on communication

Do not shorten the interval timing between the start and stop of isochronous communication.

In case where the start and stop of isochronous communication are continuously processed, the next instructions are not accepted during image data transfer until the frame is terminated even if a camera receives stop instructions. Therefore, leave an interval of one frame until the next instructions are started after image communication stops.

[MEMO]



Technoscope Co., Ltd.

7-6-13 Kishi-cho Urawa-ku Saitama City, Saitama 336-0064

TEL. 048-822-5281 FAX. 048-822-5285